

# Double-Take<sup>®</sup> AVAILABILITY<sup>™</sup>

Version 7.0

Double-Take Availability for vSphere User's Guide



## Notices

Double-Take Availability for vSphere User's Guide Version 7.0, Friday, December 13, 2013

Check the Vision Solutions support web site at <http://www.VisionSolutions.com/SupportCentral> for the most up-to-date version of this documentation.

- **Product Updates**—Check your service agreement to determine which updates and new releases you may be eligible for. Product updates can be obtained from the support web site at <http://www.VisionSolutions.com/SupportCentral>.
- **Sales**—If you need maintenance renewal, an upgrade activation code, or other sales assistance, contact your reseller/distributor or a Vision Solutions sales representative. Contact information is available on the Vision Solutions Worldwide Locations and Contacts web page at <http://www.VisionSolutions.com/Company/Vision-HA-Locations.aspx>.
- **Technical Support**—If you need technical assistance, you can contact CustomerCare. All basic configurations outlined in the online documentation will be supported through CustomerCare. Your technical support center is dependent on the reseller or distributor you purchased your product from and is identified on your service agreement. If you do not have access to this agreement, contact CustomerCare and they will direct you to the correct service provider. To contact CustomerCare, you will need your serial number and activation code. Contact information is available on the Vision Solutions CustomerCare web page at <http://www.VisionSolutions.com/Support/Support-Overview.aspx>.
- **Professional Services**—Assistance and support for advanced configurations may be referred to a Pre-Sales Systems Engineer or to Professional Services. For more information, see the Windows and Linux tab on the Vision Solutions Consulting Services web page at <http://www.VisionSolutions.com/Services/Consulting-Services.aspx>.
- **Training**—Classroom and computer-based training are available. For more information, see the Double-Take Product Training web page at <http://www.VisionSolutions.com/Services/DT-Education.aspx>.
- **Documentation**—Please forward any comments or suggestions about this documentation to [documentation-Double-Take@VisionSolutions.com](mailto:documentation-Double-Take@VisionSolutions.com).

This documentation is subject to the following: (1) Change without notice; (2) Furnished pursuant to a license agreement; (3) Proprietary to the respective owner; (4) Not to be copied or reproduced unless authorized pursuant to the license agreement; (5) Provided without any expressed or implied warranties, (6) Does not entitle Licensee, End User or any other party to the source code or source code documentation of anything within the documentation or otherwise provided that is proprietary to Vision Solutions, Inc.; and (7) All Open Source and Third-Party Components ("OSTPC") are provided "AS IS" pursuant to that OSTPC's license agreement and disclaimers of warranties and liability.

Vision Solutions, Inc. and/or its affiliates and subsidiaries in the United States and/or other countries own/hold rights to certain trademarks, registered trademarks, and logos. Hyper-V and Windows are registered trademarks of Microsoft Corporation in the United States and/or other countries. Linux is a registered trademark of Linus Torvalds. vSphere is a registered trademark of VMware. All other trademarks are the property of their respective companies. For a complete list of trademarks registered to other companies, please visit that company's website.

© 2013 Vision Solutions, Inc. All rights reserved.

# Contents

<b>Chapter 1 Agentless vSphere overview</b>	<b>4</b>
Replication process	5
<b>Chapter 2 Agentless vSphere requirements</b>	<b>7</b>
<b>Chapter 3 Getting started</b>	<b>10</b>
Installing the Double-Take replication or controller appliance	11
Installing the Double-Take Console	19
Adding controller appliances	21
Licensing a controller appliance	22
Adding replication appliances	24
Creating an agentless vSphere job	25
<b>Chapter 4 Managing and controlling agentless vSphere jobs</b>	<b>40</b>
Viewing agentless vSphere job details	47
Validating an agentless vSphere job	50
Editing an agentless vSphere job	51
Viewing an agentless vSphere job log	52
Updating to a new controller appliance	54
Failing over agentless vSphere jobs	55
<b>Chapter 5 Double-Take Console</b>	<b>56</b>
Double-Take Console requirements	57
Console options	58
<b>Chapter 6 Managing servers</b>	<b>60</b>
Providing server credentials	66
Viewing server details	67
Editing server properties	69
Controller appliance associations properties	70
Server licensing	71
E-mail notification configuration	73
Viewing server logs	75

---


## Chapter 1 Agentless vSphere overview

The fundamental function of Double-Take is to identify what you want to protect on your production server, known as the source, and replicate that to a backup server, known as the target. With agentless vSphere protection, there are multiple components which make up the source and target.

1. You need your hosts. (The use of the word host is used generically to represent a standalone ESXi host or a cluster, which is typically defined as a group of ESXi hosts.) One is your source host and one is your target host. In some cases, the source and target could be the same host.
2. You need virtual machines on your source host. These are the virtual machines you want to protect and are called your source virtual machines. Once you have established protection, you will have replicas of the source virtual machines on your target host. These are called your target virtual machines.
3. Each source and target host must have a replication appliance, which controls sending data between the hosts. These replication appliances are referred to as the source replication appliance and the target replication appliance.

Beyond your source and target components, you need a controller appliance. The controller appliance handles communication from the Double-Take Console to the replication appliances. It also handles licensing for your agentless vSphere jobs. The controller appliance should not be located with your source host, in case your source host experiences a failure. Ideally, the controller appliance should be located with your target host or on its own.


You must also have the Double-Take Console in your environment.



1. The Double-Take Console communicates with the Double-Take controller appliance.
2. The controller appliance communicates with the various Double-Take replication appliances.
3. The replication appliances on the source take the replication snapshots and send them to the target. The replication appliances on the target apply the replication snapshots and take point-in-time snapshots of the target. For more details on the replication process, see *Replication process* on page 5.

# Replication process

Agentless vSphere protection is different than other Double-Take job types because it is reliant on ESXi technology. Instead of real-time replication, agentless vSphere protection takes snapshots of your source virtual machine and replicates those snapshots to the target host where they are applied to the target virtual machine. The following diagram illustrates a typical agentless vSphere protection job. In this example, the replication interval is 15 minutes. Additionally, the example accounts for taking point-in-time snapshots of the target virtual machine. The example point-in-time snapshot interval is one hour. The job is started at 8:00.



1. This is your first replication interval. It occurs between 8:00 and 8:15.
  - 1.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 1.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run. Since this is your first replication interval and scheduled snapshots are enabled, a point-in-time snapshot of the target virtual machine will be triggered.
  - 1.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.
  - 1.4. Double-Take takes a point-in-time snapshot of the target virtual machine.
  - 1.5. Because the 15 minute replication interval has not been exhausted, Double-Take waits until the next replication interval is scheduled.
2. This is your second replication interval. It occurs between 8:15 and 8:35.
  - 2.1. Again, Double-Take takes a replication snapshot of the source virtual machine.
  - 2.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run. Because the point-in-time snapshot schedule of one hour has not elapsed, a point-in-time snapshot of the target virtual machine will not be triggered.
  - 2.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.

In this replication interval, the process took longer than the 15 minutes allocated, so there is no delay before the next replication interval starts. Double-Take logs a message when this occurs.
3. This is your third replication interval. It occurs between 8:35 and 8:50.
  - 3.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 3.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run, but it is not time yet.
  - 3.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.
  - 3.4. Double-Take waits until the next replication interval is scheduled.

4. This is your fourth replication interval. It occurs between 8:50 and 9:05.
  - 4.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 4.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run, but it is not yet because it has only been 50 minutes since the job started.
  - 4.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.
  - 4.4. Double-Take waits until the next replication interval is scheduled.
5. This is your fifth replication interval. It occurs between 9:05 and 9:20.
  - 5.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 5.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run. At this point, it has been one hour since the job started, so a point-in-time snapshot of the target virtual machine will be triggered.
  - 5.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.
  - 5.4. Double-Take takes a point-in-time snapshot of the target virtual machine.
  - 5.5. Double-Take waits until the next replication interval is scheduled.
6. This is your sixth replication interval. It occurs between 9:20 and 10:25.
  - 6.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 6.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run. There is not because it has not been one hour since the last point-in-time snapshot.
  - 6.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.

This replication interval took one hour and five minutes. Notice that the replication interval is set for every 15 minutes, but a new interval will not be started while a current interval is running.
7. This is your seventh replication interval. It occurs between 10:25 and 10:40.
  - 7.1. Double-Take takes a replication snapshot of the source virtual machine.
  - 7.2. Double-Take checks to see if a scheduled point-in-time snapshot is due to run. It has been one hour since the last point-in-time snapshot, so a new point-in-time snapshot of the target virtual machine will be triggered.
  - 7.3. Double-Take replicates and applies the replication snapshot of the source virtual machine to the target virtual machine.
  - 7.4. Double-Take takes a point-in-time snapshot of the target virtual machine.
  - 7.5. Double-Take waits until the next replication interval is scheduled.

---

## Chapter 2 Agentless vSphere requirements

The configuration of an agentless vSphere job is different than other Double-Take jobs. Review the *Agentless vSphere overview* on page 4 first and then make sure your environment meets the following requirements.

- **ESXi hosts**—Your source and target hosts must be running one of the following ESXi versions. Note that this is ESXi that is supported. ESX is not supported.
  - ESXi 5.0 Update 2 Essentials, Essentials Plus, Standard, Enterprise, or Enterprise Plus
  - ESXi 5.1 Essentials, Essentials Plus, Standard, Enterprise, or Enterprise Plus
  - ESXi 5.5 Essentials, Essentials Plus, Standard, Enterprise, or Enterprise Plus
- **vCenter**—vCenter is not required, but if you are using it, then you must use version 5.0 or later.
- **vCenter permissions**—If you want to limit the permissions required for the vCenter account that you will be using for your agentless vSphere job, your account must have at a minimum the permissions listed below.
  - **Datastore**—Allocate space, Browse datastore, Low level file operations, Remove file, and Update virtual machine files
  - **Global**—Act as vCenter server and Licenses
  - **Host, Local Operations**—Create virtual machine, Delete virtual machine, Reconfigure virtual machine, and Relayout snapshots
  - **Network**—Assign Network
  - **Resource**—Assign virtual machine to resource pool
  - **Virtual Machine**—All virtual machine permissions are required.
- **vMotion**—Host vMotion is only supported if you are using vCenter. Storage vMotion is not supported.
- **ESXi and vCenter interoperability**—Any combination of ESXi and vCenter or ESXi standalone host is supported, with the following exceptions.
  - VMware does not support 5.1 ESXi hosts on a 5.0 vCenter.
  - VMware does not support 5.5 ESXi hosts on a 5.0 vCenter.
  - Double-Take does not support the following source to target combinations.
    - 5.1 ESXi standalone host to a 5.0 ESXi standalone host
    - 5.1 ESXi standalone host to a 5.0 ESXi host on a 5.0 vCenter
    - 5.1 ESXi host on a 5.1 vCenter to a 5.0 ESXi standalone host
    - 5.1 ESXi host on a 5.1 vCenter to a 5.0 ESXi host on a 5.0 vCenter
- **Source virtual machines**—Your source virtual machines must meet the following requirements and limitations.
  - Each virtual machine must be hardware version 8 or later.
  - If your virtual machine is using hardware version 9, you will not be able to use ESXi version 5.0. This is a VMware limitation.

- If your virtual machine is using hardware version 10, you will not be able to use ESXi version 5.0 or 5.1. This is a VMware limitation.
- **Operating system**—The following guest operating systems are supported on the source virtual machine.
  - **Windows**—Windows 2003, Windows 2008, Windows 2008 R2, Windows 2012, and Windows 2012 R2
  - **Linux**—Ubuntu 10.04 and 12.04, Redhat and CentOS 5 and 6, and SuSE 10 and 11
- **Raw device mapping**—You cannot use raw device mapping (RDM).
- **Change block tracking**—Change block tracking must be supported on the source virtual machines, specifically the `changeTrackingSupported` flag must be set to true. See your VMware documentation for details on change block tracking.
- **Independent disks**—Independent disks are not supported because VMware cannot take a snapshot of an independent disk, and Double-Take agentless vSphere replication technology is based on VMware snapshots.
- **Appliances**—Your controller appliance and your replication appliances will be an OVF (Open Virtualization Format) virtual machine included with Double-Take. You must install these appliances before you can establish protection. See *Installing the Double-Take replication or controller appliance* on page 11 for installation instructions. Keep in mind the following caveats for controller and replication appliances.
  - The appliances are pre-configured for optimal performance for most typical environments. While not required, you can modify memory, CPU, and other configurations to fit your specific environment.
  - You should not install or run anything else on these appliances. They must be dedicated to Double-Take processing only. Do not use them for any other activity (web server, database server, and so on).
  - The firewall is disabled and should remain disabled.
  - A single replication appliance can protect a maximum of 59 virtual disk files (.vmdk files). For example, if your virtual machines each have four disk files, you can protect 14 virtual machines ( $14 \times 4 = 56$ ). You may want to balance the replication among multiple replication appliances, depending on various factors such as the number of virtual machines you are protecting and the replication interval for your jobs.
  - Because the controller appliance controls licensing for all of your replication appliances, the date and time (relative to UTC) on all of the appliances should be the same or within a few seconds of each other. Time differences could cause license invalidation.
- **Protocols and networking**—Your servers must meet the following protocol and networking requirements.
  - Your servers and appliances must have TCP/IP with static IP addressing.
  - IPv4 is the only supported version.
  - If you use DNS, you must have the appliances names and IP addresses in a forward lookup zone in DNS. Additionally, you must have the subnet the appliances will be using in a reverse lookup zone in DNS.
  - If you are not using DNS, you must configure the hosts file on each controller appliance and replication appliance to include mappings for all other replication appliances, controller appliances, vCenters, and ESXi servers.



- **Snapshots**—You can use third party tools to take snapshots of the source. Keep in mind the VMware snapshot limits for your version and that Double-Take requires one snapshot of the source, otherwise Double-Take replication will not work. Double-Take will delete its own snapshot on the source at the end of each replication interval.

Third party snapshots of the replica on the target is not supported. You can take Double-Take point-in-time snapshots on the target if needed. Again, keep in mind the VMware snapshot limit for your version and that Double-Take requires at least two replication snapshots on the target in order for replication to work. Double-Take will account for the two replication snapshots by limiting the maximum number of point-in-time snapshots. Also Double-Take will delete any more than two replication snapshots on the target.

- **Supported configurations**—The following table identifies the supported host configurations for an agentless vSphere job. (These are source and target configurations for the ESXi or vCenter host, not the virtual machines or appliances.)

Configuration		Supported	Not Supported
Source host to target host configuration <sup>1</sup>	One to one, active/standby	X	
	One to one, active/active	X	
	Many to one	X	
	One to many	X	
	Chained		X
	Single host/cluster	X	
Host configuration	Standalone to standalone	X	
	Standalone to cluster	X	
	Cluster to standalone	X	
	Cluster to cluster	X	
Upgrade configuration	Upgrade 5.3 Double-Take Availability for VMware Infrastructure job to 7.0 agentless vSphere job		X
Version 7.0 console	Version 7.0 console can view or create jobs for 5.3 source and 5.3 target		X

1. See *Supported configurations* in the Double-Take Console online help for details on each of the source to target configurations.

---

## Chapter 3 Getting started

To understand how agentless vSphere protection works, see *Agentless vSphere overview* on page 4 and *Replication process* on page 5. These two sections will explain how your environment should be configured for agentless vSphere protection and how the replication process works, which is different than the replication process for other Double-Take job types.

When you are ready to begin, you will need to complete the following steps, in order.

1. Review the *Agentless vSphere requirements* on page 7 to make sure your environment meets the requirements.
2. Install Double-Take on your controller and replication appliances. See *Installing the Double-Take replication or controller appliance* on page 11.
3. Install the Double-Take Console on a Windows machine. See *Installing the Double-Take Console* on page 19.
4. Add your controller appliance to your Double-Take Console. See *Adding controller appliances* on page 21.
5. Add your licenses to your controller appliance. See *Licensing a controller appliance* on page 22.
6. Add your replication appliances to your controller appliance. See *Adding replication appliances* on page 24.
7. Create your agentless vSphere job. See *Creating an agentless vSphere job* on page 25.

Once your job is created and running, see the following sections to manage your job.

- *Managing and controlling agentless vSphere jobs* on page 40—You can view status information about your job and learn how to control the job.
- *Controller appliance associations properties* on page 70—View and manage the associated replication appliances and manage your controller appliance's licensing.
- *Failing over agentless vSphere jobs* on page 55—Use this section when a failover condition has been met or if you want to failover manually.

# Installing the Double-Take replication or controller appliance

You will need to install both the Double-Take replication and controller appliances. See *Agentless vSphere overview* on page 4 for an overview of what appliances you need for your environment.

You have the choice of installing an OVF (Open Virtualization Format) pre-packaged virtual machine or installing the software on your own pre-formatted virtual machine.



If you already have an existing Double-Take replication or controller appliance that you want to upgrade, use the instructions *Upgrading your appliances* on page 17.

---

## Deploying the OVF virtual machine on vCenter

1. Locate the .ova installation file either on your Double-Take DVD or from the location where you downloaded it.
  - **Replication appliance**—The installation file name for the replication appliance will be similar to dtav\_ra\_7.0.0.1124.0.ova, depending on the Double-Take version number.
  - **Controller appliance**—The installation file name for the controller appliance will be similar to dtav\_ca\_7.0.0.1124.0.ova, depending on the Double-Take version number.
2. If necessary, copy the .ova file to a location that is accessible from your vSphere client.
3. From your vSphere client, select the root of your tree, select **File, Deploy OVF Template**, and specify the replication or controller appliance .ova file. Click **Next** to continue.
4. Review the OVF template details and click **Next** to continue.
5. Review the Vision Solutions license agreement. You must accept the license agreement by clicking **Accept**. Click **Next** to continue.
6. Specify the name of the virtual machine. This is the name that will be displayed in vCenter.
7. Specify the inventory location where you want to install the appliance. If this is your source replication appliance, this should be the same datacenter where your source ESXi host is located. If this is your target replication appliance, this should be the same datacenter where your target ESXi host is located.
8. Click **Next** to continue.
9. Select the ESXi host or cluster where you want to install the appliance. If this is your source replication appliance, this should be your source ESXi host. If this is your target replication appliance, this should be your target ESXi host. Click **Next** to continue.
10. If desired, select the resource pool where you want to install the appliance. You will not have this option if you do not have resource pools. Click **Next** to continue.
11. Select the datastore where you want to store the appliance files. Make sure the datastore has at least 16 GB of space available. Click **Next** to continue.
12. Select the type of disk to create. The names you see displayed will be dependent on your vSphere client.
  - **Flat or Thick Provision Lazy Zeroed**—This disk type allocates the full amount of the disk space immediately, but does not initialize the disk space to zero until it is needed.

- **Thick or Thick Provision Eager Zeroed**—This disk type allocates the full amount of the disk space immediately, initializing all of the allocated disk space to zero.
  - **Thin Provision**—This disk type does not allocate the disk space until it is needed.
13. Click **Next** to continue.
  14. If your selected ESXi host or cluster has multiple networks, map the network on the appliance to a network on your ESXi host, and click **Next** to continue.
  15. Assign the virtual machine and network properties. If you are using DNS, make sure you are using the same IP address that you specified in DNS.
    - **Root password**—Set a password for the root login. If you do not make a change, the default password will be used. The default password is vision.
    - **Time zone setting**—Select the virtual machine's time zone. The default setting is UTC.
    - **Hostname**—Specify the hostname or full qualified domain name to assign to the virtual machine. Make sure this is the same name that you specified in DNS.
    - **Default gateway**—Specify the virtual machine's default gateway.
    - **DNS server**—Specify the virtual machine's DNS server.
    - **Network IP address**—Specify the IP address to assign to the virtual machine. You must use an IPv4 address.
    - **Network subnet mask**—Specify the subnet mask for the assigned IP address.



If you use DNS, you must have the appliances names and IP addresses in a forward lookup zone in DNS. Additionally, you must have the subnet the appliances will be using in a reverse lookup zone in DNS. If you are not using DNS, you must configure the hosts file on each controller appliance and replication appliance to include mappings for all other replication appliances, controller appliances, vCenters, and ESXi servers.

16. Click **Next** to continue.
17. Review the **Deployment settings**. If you want to make any changes, click **Back**. If not, enable the **Power on after deployment** option and click **Finish**.
18. After the appliance deployment is complete, click **Close**.

Once you have installed your appliances, you will need to install the Double-Take Console. See *Installing the Double-Take Console* on page 19. After you have installed the console, you can add the appliances to the Double-Take Console and create associations between them. See *Adding controller appliances* on page 21 and *Adding replication appliances* on page 24. Then you can create your agentless vSphere job to protect your virtual machines.



Once the appliance has been installed and configured, you should not need to access or use it. However, if you need to change any network settings, you can modify them using the **Configure Network** menu on the appliance or by using the web interface by going to [https://ip\\_address:5480](https://ip_address:5480), where ip\_address is the current IP address of the appliance. Keep in mind if you change the network settings using the web interface, you will lose your connection to that interface because it will still be using the original IP address.

The appliance menu runs as root, so make sure you take advantage of VMware security to restrict access to the appliance. See your VMware documentation for details on limiting access to the appliance's console.

---

## Deploying the OVF virtual machine on standalone ESXi

1. Locate the .ova installation file either on your Double-Take DVD or from the location where you downloaded it.
  - **Replication appliance**—The installation file name for the replication appliance will be similar to dtav\_ra\_7.0.0.1124.0.ova, depending on the Double-Take version number.
  - **Controller appliance**—The installation file name for the controller appliance will be similar to dtav\_ca\_7.0.0.1124.0.ova, depending on the Double-Take version number.
2. If necessary, copy the .ova file to a location that is accessible from your vSphere client.
3. From your vSphere client, select the root of your tree, select **File, Deploy OVF Template**, and specify the replication or controller appliance .ova file. Click **Next** to continue.
4. Review the OVF template details and click **Next** to continue.
5. Review the Vision Solutions license agreement. You must accept the license agreement by clicking **Accept**. Click **Next** to continue.
6. Specify the name of the virtual machine. This is the name that will be displayed in the inventory. Click **Next** to continue.
7. Select the datastore where you want to store the appliance files. Make sure the datastore has at least 16 GB of space available. Click **Next** to continue.
8. Select the type of disk to create. The names you see displayed will be dependent on your vSphere client.
  - **Flat or Thick Provision Lazy Zeroed**—This disk type allocates the full amount of the disk space immediately, but does not initialize the disk space to zero until it is needed.
  - **Thick or Thick Provision Eager Zeroed**—This disk type allocates the full amount of the disk space immediately, initializing all of the allocated disk space to zero.
  - **Thin Provision**—This disk type does not allocate the disk space until it is needed.
9. Click **Next** to continue.
10. If your selected ESXi host or cluster has multiple networks, map the network on the appliance to a network on your ESXi host, and click **Next** to continue.
11. Review the **Deployment settings**. If you want to make any changes, click **Back**. If not, enable the **Power on after deployment** option and click **Finish**.
12. When the deployment is complete, power on the virtual machine.
13. After the boot process is complete, you will be prompted to set a password for the root login. If you do not make a change, the default password will be used. The default password is vision.
14. After you enter and confirm the password, you will be prompted to set the time zone. The default setting is UTC.
15. When the boot process finishes, you will be at the appliance's main menu. Select **Configure Network**.
16. Select option 3 to specify the **Hostname** to assign to the virtual machine. Make sure this is the same name that you specified in DNS.
17. Set the network properties (options 2, 4, and 6) to assign the virtual machines default gateway, DNS server, IP address (IPv4) and the subnet mask.



If you use DNS, you must have the appliances names and IP addresses in a forward lookup zone in DNS. Additionally, you must have the subnet the appliances will be using in a reverse lookup zone in DNS. If you are not using DNS, you must configure the hosts file on each controller appliance and replication appliance to include mappings for all other replication appliances, controller appliances, vCenters, and ESXi servers.

---

18. When your settings are complete, restart the appliance to apply the new settings.

---



Once the appliance has been installed and configured, you should not need to access or use it. However, if you need to make additional changes, you can use the options on the main menu or use the web interface by going to [https://ip\\_address:5480](https://ip_address:5480), where ip\_address is the current IP address of the appliance. Keep in mind if you change the network settings using the web interface, you will lose your connection to that interface because it will still be using the original IP address.

The appliance menu runs as root, so make sure you take advantage of VMware security to restrict access to the appliance. See your VMware documentation for details on limiting access to the appliance's console.

---

## ***Installing the appliance manually***

Before you begin the manual appliance installation, you must have an existing VMware hosted virtual machine that meets the following requirements.

- The virtual machine must be running Ubuntu 10.04.x AMD64 edition.
- The virtual machine must have at least 4 GB of virtualized physical RAM.
- The virtual machine must have at least two CPUs (two virtual sockets, not two virtual cores).
- The virtual machine must have at least 16 GB of disk space available.
- The virtual machine must have a valid, working network configuration. If you use DNS, you must have the appliances names and IP addresses in a forward lookup zone in DNS. Additionally, you must have the subnet the appliances will be using in a reverse lookup zone in DNS. If you are not using DNS, you must configure the hosts file on each controller appliance and replication appliance to include mappings for all other replication appliances, controller appliances, vCenters, and ESXi servers.
- The virtual machine must be dedicated to Double-Take processing only. Do not use the virtual machine for any other activity (web server, database server, and so on).
- Make sure you review the *Agentless vSphere requirements* on page 7 for any other requirements not specifically defined here.

Locate and install the .deb installation file on your virtual machine. You can find the file either on your Double-Take DVD or from the location where you downloaded it.

- **Replication appliance**—The installation file name for the replication appliance will be similar to dtav\_ra\_7.0.0.1124.0.deb, depending on the Double-Take version number.
- **Controller appliance**—The installation file name for the controller appliance will be similar to dtav\_ca\_7.0.0.1124.0.deb, depending on the Double-Take version number.

Once you have installed your appliances, you will need to install the Double-Take Console. See *Installing the Double-Take Console* on page 19. After you have installed the console, you can add the appliances to the Double-Take Console and create associations between them. See *Adding controller appliances* on page 21 and *Adding replication appliances* on page 24. Then you can create your agentless vSphere job to protect your virtual machines.



## Upgrading your appliances

The process for upgrading your replication and controller appliances is partly manual and partly automatic. A single controller appliance, along with its associated replication appliances, are upgraded together in one operation. Steps for upgrading are listed below.

1. Download the upgrade file called dtav-upgrade.zip to a temporary folder on the Windows machine running the Double-Take Console.
2. If you do not already have it installed, download and install Java from <http://www.java.com/en/download/manual.jsp> to that same Windows machine.
3. Using the Double-Take Console, stop all jobs associated with the controller appliance and the replication appliances you are upgrading.
4. Close the Double-Take Console.
5. Extract (unzip) dtav-upgrade.zip, which will create a subfolder called dtav-upgrade.
6. In the dtav-upgrade subfolder, open dtav-upgrade.bat in a text editor.
7. Modify the IP addresses and user credentials to match your controller appliance and its associated replication appliances. Do not edit below the line of ##### signs.

For example, your batch file will look similar to the following.

```
@echo off
set ControllerHostName=172.31.39.145
set ControllerUserName=user_name
set ControllerPassword=password
set RA1=172.31.39.143: user_name: password
set RA2=172.31.39.144: user_name: password

:#####
```

8. If necessary, add additional replication appliances that are associated with your controller by repeating the set RA commands and incrementing the RA counter. For example, you might add the following lines after the set RA2 command.  
  
set RA3=172.31.39.210: user\_name: password  
set RA4=172.31.39.211: user\_name: password
9. Save the changes to the dtav-upgrade.bat file and close it.
10. Run the dtav-upgrade.bat file by double-clicking on it from a Windows explorer window or from a command line. You will see brief log messages showing the upgrade progress.

```
C:\Windows\system32\cmd.exe
172.31.39.145: installing dtcs
172.31.39.143: installing dtms
172.31.39.144: installing dtms
dpkg -l: ii  dtav-ra              7.0.0.1658.0
          DTAU Management Service
dpkg -l: ii  dtav-ca              7.0.0.1658.0
          DTAU Controller Service
dpkg -l: ii  dtav-ra              7.0.0.1658.0
          DTAU Management Service
172.31.39.145: starting DTAU Controller
172.31.39.143: starting DTAU Management
172.31.39.145: done
172.31.39.143: done
172.31.39.144: starting DTAU Management
172.31.39.144: done

Upgrade complete

Press any key to continue . . .
```

11. If you have additional controller appliances to upgrade, repeat the steps to stop the jobs associated with those controller appliances and then modify and run the batch file for those controller and replication appliances.
12. Once the upgrades are complete, reopen the Double-Take Console and restart the jobs. The jobs will resume from where they left off in the replication process.



If an upgrade fails for any appliance you can repeat the script execution, even if some of the appliances upgraded successfully.

---

# Installing the Double-Take Console

The Double-Take Console must be installed on a Windows machine. See *Double-Take Console requirements* on page 57 for specific details.

1. Close any open applications.
2. Start the installation program using the appropriate instructions, depending on your media source.
  - **Physical media**—If auto-run is enabled, the installation program will start automatically. To manually start the program, run `autorun.exe` from your physical media.
  - **Web download**—Launch the `.exe` file that you downloaded from the web.
3. When the installation program begins, the Autorun appears allowing you to install software and view documentation and online resources. To install the console, , select the **Install Double-Take Availability** link.
4. Depending on your version of Windows and the components you have installed, you may see an initial screen indicating that you need to install or enable Microsoft .NET Framework. If you do not see this screen, your server already has the appropriate version of Microsoft .NET. You must install or enable Microsoft .NET before installing Double-Take. Select **Yes** to install or enable Microsoft .NET and click **Continue**.
5. You will be given the opportunity to check for a more recent version of the software.
  - If you do not want to check for a later version, select **No** and click **Next**.
  - If you want to check for a later version, select **Yes** and click **Next**. The installation program will establish an Internet connection from your server to the Vision Solutions web site.
    - If later versions are found, they will be listed. Highlight the version you want and either download that version and install it automatically or download that version and exit the installation. (If you exit the installation, you can run the updated installation later directly from the location where you saved it.)
    - If no later versions are found, continue with the current installation.
    - If an Internet connection cannot be established, continue with the current installation or install a previously downloaded version.
6. Review the Vision Solutions license agreement. You must scroll through and review the entire license agreement. You must accept the license agreement in order to continue with the installation program. Click **Next** to continue.
7. Review the activation notice. Most Double-Take licenses require activation after installation for full product functionality. Failure to activate licenses that require it will cause your Double-Take jobs to fail. See *Licensing a controller appliance* on page 22 for more details.
8. Click **OK** to continue.
9. Select the **Client Components Only** installation option. The client components do not require an activation code, but are required to administer Double-Take servers throughout the organization.
10. If desired, specify where the Double-Take files will be installed by clicking **Change**, specifying a location, and then clicking **OK**.
11. Click **Next** to continue.
12. If the machine where you are installing has Windows Firewall enabled, you will be given the opportunity to open and reassign any firewall ports for Double-Take use.
  - **Open only the ports that are not in use**—This option will open any firewall ports that are not in use. The ports that are opened will be assigned to Double-Take.

- **Open all ports, reassigning the ports in use to Double-Take**—This option will open all necessary firewall ports, reassigning any to Double-Take as needed.
  - **Do not configure the Windows Firewall at this time**—This option will not modify any firewall ports. If you select this option, you will have manually modify your firewall settings for Double-Take processing.
13. Click **Next** to continue.
  14. If you are satisfied with the selections you have made and are ready to begin copying the Double-Take files, click **Install**.
  15. After the files have completed copying, click **Finish** to exit the installation program.

# Adding controller appliances

The first time you start the console, the **Manage Servers** page is empty. In order to protect and monitor your virtual machines, you must insert your controller appliance in the console.

1. Select **Get Started** from the toolbar.
2. Select **Add servers** and click **Next**.
3. On the **Manual Entry** tab, specify the controller appliance information.
  - **Server**—This is the name or IP address of the controller appliance to be added to the console.
  - **User name**—Specify the root user or another user that has the administrator role on the appliance.
  - **Password**—Specify the password associated with the **User name** you entered.
4. You can expand the **More Options** section to configure the following settings.
  - **Domain**—If you are working in a domain environment, specify the **Domain**.
  - **Associate with Double-Take Linux Appliance**—This field is not applicable to agentless vSphere jobs.
5. After you have specified the appliance information, click **Add**.
6. Do not insert your replication appliances. The replication appliances will be inserted into the console using the Add Replication Appliances pages. See *Adding replication appliances* on page 24.
7. If you need to remove appliances from the list of **Servers to be added**, highlight it and click **Remove**. You can also remove all of them with the **Remove All** button.
8. When your list of **Servers to be added** is complete, click **OK**.

# Licensing a controller appliance

You must apply a Double-Take license to an appliance using the console.

1. Make sure you have your appliance inserted in the console.
2. From the **Manage Servers** page, double-click on the server to view the server's details.
3. From the **View Server Details** page, click on the **Edit server properties** link.
4. Expand the **Licensing** section.
5. Licensing identifies your Double-Take activation codes.



The fields and buttons in the **Licensing** section will vary depending on your Double-Take Console configuration and the type of activation codes you are using.

---

- **Add activation codes and activation keys**—The activation code and activation key are the Double-Take license which is required on every Double-Take server. They are a 24 character, alpha-numeric code. You can change your activation code without reinstalling, if your license changes.

There are different licenses available depending on the Double-Take product you are using. Agentless vSphere jobs use a quantity license to license a specific number of jobs. See **Total licenses quantity** below for details on how the license quantity (used by the controller appliance) is allocated for agentless vSphere jobs.

To add an activation code and activation key, type in the code and click **Add**. If your console has been enabled to manage your license inventory, click **Choose from inventory** to open the Activation Codes dialog box where you can select the activation codes you want to apply. See *Console options* on page 58 for details on enabling the license inventory.



The license inventory feature cannot be enabled if your service provider has restricted access to it.

---

- **Current activation codes**—The server's current activation codes are displayed.
  - **Warning or error icon**—Warnings indicate the license is temporary and will expire. Errors indicate the license has expired.
  - **Product**—The product associated with the license
  - **Serial Number**—The serial number associated with the license
  - **Expiration Date**—The date the license expires, if there is one
  - **Activation Code**—The activation code

To remove a code, highlight it and click **Remove**. To copy a code, highlight it and click **Copy**.

- **Activation**—If your activation code needs to be activated, you will see an additional **Activation** section at the bottom of the **Licensing** section. To activate your code, use one of the following procedures.

- **Activate online**—If you have Internet access, you can activate your license and apply the activated license to the server in one step. Select **Activate Online**. You will not be able to activate a license that has already been activated but has not been deactivated. In that case, you will be prompted to complete a host transfer. Ideally, you should deactivate the license instead of doing a host transfer. See the Double-Take Console online help for details on deactivating licenses and host transfers.
- **Obtain activation key online, then activate**—If you have Internet access, click the hyperlink in the **Activation** section to take you to the web so that you can submit your activation information. Complete and submit the activation form, and you will receive an e-mail with the activation key. Activate your server by entering the activation key in the **Add activation codes and activations keys** field and clicking **Add**.
- **Obtain activation key offline, then activate**—If you do not have Internet access, go to <https://activate.doubletake.com> from another machine that has Internet access. Complete and submit the activation form, and you will receive an e-mail with the activation key. Activate your server by entering the activation key in the **Add activation codes and activations keys** field and clicking **Add**.

The permanent code is specific to this server. It cannot be used on any other server. If the activation code and server do not match, Double-Take will not run.



If your activation codes needs to be activated, you will have 14 days to do so.

If you rename a server that has already has a Double-Take license applied to it, for example if you rebuild a server, you will have to perform a host-transfer to continue using that license. This includes changing the case (capitalization) of the server name (upper or lower case or any combination of case).

---

6. Once you have completed your licensing, click **OK** to return to the **Manage Servers** page.

# Adding replication appliances

From the **Add Replication Appliances** page, you can associate replication appliances to controller appliances.

- **Controller appliance**—Select a controller appliance from the list. The replication appliances you add on this page will be associated with the controller appliance you select.
- **vCenter/ESXi server**—Specify the IP address of the vCenter or ESXi server that is hosting the replication appliance the selected controller appliance will communicate with. If you are using vCenter, specify your vCenter. Only specify your ESXi server if it is a standalone server. If you are not using the default vCenter/ESXi port, you can specify the port number that you are using by entering IP\_address:port\_number. For example, you might enter 172.31.139.10:1124.
  - **User name**—Specify the root user or another user that has the administrator role on the specified server.
  - **Password**—Specify the password associated with the **User name** that you entered.
- **Replication appliance**—Specify the IP address of the replication appliance.
  - **User name**—Specify the root user or another user that has the administrator role on the specified replication appliance.
  - **Password**—Specify the password associated with the **User name** that you entered.


After you have configured your replication appliance to controller appliance association, click **Add**. Repeat the process to associate additional replication appliances to your controller appliance. If you need to remove any replication appliance associations from a controller appliance, highlight the appliance in the list and click **Remove**. You can also remove all of the associated replication appliances by clicking **Remove All**. Keep in mind that you cannot remove appliance associations if a job is using the appliance. You can also manage your appliance associations through the controller appliance's server properties. See *Controller appliance associations properties* on page 70.



# Creating an agentless vSphere job


Use these instructions to create an agentless vSphere job.

1. Make sure you have added your controller and replication appliances. See *Adding controller appliances* on page 21 and *Adding replication appliances* on page 24.
2. Click **Get Started** from the toolbar.
3. Select **Double-Take Availability** and click **Next**.
4. Select **Protect virtual servers on vSphere with agentless replication** and click **Next**.
5. Choose your source ESXi server. This is the ESXi server or cluster that contains the virtual machines that you want to protect. This is also where your source replication appliance is located. The list shows the ESXi servers or clusters currently associated with your controller appliance.




6. Click **Next** to continue.

7. Select the virtual machines on your source that you want to protect. A separate job will be created for each source that you select for protection. You can only select the number of virtual machines equal to the number of free licenses you have available.



8. Click **Next** to continue.
9. Choose your target ESXi server. This is the ESXi server or cluster where the replica virtual machines will be hosted. This is also where your target replication appliance is located. The list shows the ESXi servers or clusters currently associated with your controller appliance.



10. Click **Next** to continue.
11. You have many options available for your agentless vSphere job. Configure those options that are

applicable to your environment.

---



All agentless vSphere jobs will have the following sections available on the **Set Options** page.

- **Replica Virtual Machine Network Settings**
- **Virtual Switch Mappings**
- **Replication Interval**
- **Encryption**
- **Snapshots**
- **Compression**

If you are protecting just one virtual machine, you will also have the following sections.


- **General**
- **Replica Virtual Machine Location**
- **Replica Host and Replication Appliances**

If you are protecting more than one virtual machine, you will have the **Virtual Machines Mappings** section instead, which is similar to the location and appliances sections.

As you can see, if you are protecting more than one virtual machine, there are a few settings that you will not have access to during job creation. In this case, default values will be used. You can modify the default values after the jobs have been created.

---

## General



The screenshot shows a window titled 'General' with a small upward arrow icon on the left. Inside the window, there is a label 'Job name:' followed by a text input field. The input field contains the text 'Alpha to 172.31.139.50'.

For the **Job name**, specify a unique name for your job.

## Replica Virtual Machine Location

**Replica Virtual Machine Location**

Replica virtual machine display name:

Select the target datastore for the virtual machine configuration files:


Datastore ▲	Total Size	Free Space	Provisioned Space
SAN05	399.75 GB	97.67 GB	14.64 GB
SAN06	399.75 GB	315.42 GB	55.02 GB
SAN07	399.75 GB	201.82 GB	358.44 GB
SAN08	399.75 GB	134.16 GB	529.42 GB

Select the target datastore for the virtual machine hard disk files:

Source Virtual Disk	Disk Size	Disk Format	Target Datastore
[SAN07] Alpha/Alpha.vmdk	16 GB	Thin	SAN07 ▼

- **Replica virtual machine display name**—Specify the name of the replica virtual machine. This will be the display name of the virtual machine on the host system.
- **Select the target datastore for the virtual machine configuration files**—Select one of the datastores from the list to indicate where on the target you want to store the replica virtual machine configuration files. Make sure the selected datastore has enough free space. The datastore you select here will become the selected datastore in the next table.
- **Select the target datastore for the virtual machine hard disk files**—By default, the datastore you selected in the first table will be selected in this table. If desired, specify a different datastore from the **Target Datastore** list to indicate where on the target you want to store each of the replica virtual machine disk files. Make sure the selected datastore has enough free space for the size of your source (plus growth) and the source's disk format (thick, thin, or flat). Additionally, if you are going to be enabling snapshots of the replica on the target, make sure you select a datastore that has enough space for the replica virtual machine disks and the snapshots.

## Replica Host and Replication Appliances



Replica Host and Replication Appliances

Select the replica host: 172.31.139.50

Select the source and target replication appliances:

Source replication appliance: Auto Select

Target replication appliance: Auto Select

- **Select the replica host**—If your target is a cluster, select the specific server that you want to use. If your target is not a cluster, this field will automatically be populated with your target.
- **Source replication appliance**—You can specify a source replication appliance or select **Auto Select** to have Double-Take select a replication appliance for you based on the current load on all of your replication appliances.
- **Target replication appliance**—You can specify a target replication appliance or select **Auto Select** to have Double-Take select a replication appliance for you based on the current load on all of your replication appliances.

## Virtual Machines Mappings

**Virtual Machines Mappings**

For each virtual machine, select the target host, target datastore for the virtual machine configuration files and the replication appliances:

Virtual Machine	Replica Virtual Machine	Target Host	Target Datastore	Source Replication Appliance	Target Replication Appliance
alpha	alpha_Replica	172.31.139.50	SAN07	Auto Select	Auto Select
beta	beta_Replica	172.31.139.50	SAN06	Auto Select	Auto Select

Select a virtual machine above and then select the target datastore for the virtual machine hard disk files:

Source Virtual Disk	Disk Size	Disk Format	Target Datastore
[SAN1] Alpha/Alpha.vmdk	16 GB	Thin	SAN2

[Show additional target datastores information](#)

- **For each virtual machine, select the target host, target datastore for the virtual machine configuration files and the replication appliances**—The first table allows you to configure each virtual machine.
  - **Replica Virtual Machine**—Specify the name of the replica virtual machine. This will be the display name of the virtual machine on the host system.
  - **Target Host**—Select the specific server that you want to use, if your target is a cluster. If your target is not a cluster, this field will automatically be populated with your target.
  - **Target Datastore**—Specify the datastore on the target where you want to store the replica virtual machine configuration files. Make sure the selected datastore has enough free space. The datastore you select here will become the selected datastore in the next table.
  - **Source Replication Appliance**—You can specify a source replication appliance or select **Auto Select** to have Double-Take select a replication appliance for you based on the current load on all of your replication appliances.
  - **Target Replication Appliance**—You can specify a target replication appliance or select **Auto Select** to have Double-Take select a replication appliance for you based on the current load on all of your replication appliances.
- **Select a virtual machine above and then select the target datastore for the virtual machine hard disk files**—The second table is dynamically linked to the first. Select a virtual machine in the first table and configure the virtual disks for that virtual machine. Then select another virtual machine in the first table and configure the virtual disks for that virtual machine. Continue until you have configured the virtual disks for each virtual machine.
  - **Target Datastore**—By default, the datastore you selected in the first table will be selected in this table. If desired, specify a different datastore on the target where you want to store the replica virtual machine disk files. Make sure the selected datastore has enough free space for the size of your source (plus growth) and the source's disk format (thick, thin, or flat). Additionally, if you are going to be enabling snapshots of the replica on the target, make sure you select a datastore that has enough space for the replica virtual machine disks and the snapshots.
- **Show additional target datastores information**—Click this link to see storage information for the datastores on your target. This will help you select the appropriate datastore for your replica virtual machines.

## Replica Virtual Machine Network Settings



The appearance and fields in this section will vary depending on if you have chosen to protect a single virtual machine or multiple virtual machines.

**Replica Virtual Machine Network Settings**

Credentials for user name: **administrator**  
[Change...](#)

☒ Use advanced settings for replica virtual machine network configuration.

Network adapters:  
Local Area Connection (172.31.206.200)

Source IP addresses:

IP Address	Subnet Mask
112.42.74.29	255.255.0.0

Replica IP addresses:

IP Address	Subnet Mask
112.52.74.29	255.255.0.0

[Add](#) [Remove](#)

Source Default Gateways:  
112.42.48.9

Replica Default Gateways:  
112.52.48.9 [↑](#) [↓](#) [Add](#) [Remove](#)

Source DNS Server addresses:  
112.42.48.20

Replica DNS Server addresses:  
112.52.48.20 [↑](#) [↓](#) [Add](#) [Remove](#)

**Replica Virtual Machine Network Settings**

Virtual machines:

Virtual Machine	Credentials	Advanced Network
Alpha	administrator	<input checked="" type="checkbox"/>
Beta	administrator	<input checked="" type="checkbox"/>

1 virtual machines selected.  
[Provide Credentials...](#) [Set Gateway...](#) [Set DNS...](#)

Network adapters:  
Local Area Connection (112.42.74.29)

Source IP addresses:

IP Address	Subnet Mask
112.42.74.29	255.255.0.0

Replica IP addresses:

IP Address	Subnet Mask
112.52.74.29	255.255.0.0

[Add](#) [Remove](#)

Source Default Gateways:  
112.42.48.9

Replica Default Gateways:  
112.52.48.9 [↑](#) [↓](#) [Add](#) [Remove](#)

Source DNS Server addresses:  
112.42.48.20

Replica DNS Server addresses:  
112.52.48.20 [↑](#) [↓](#) [Add](#) [Remove](#)

If your virtual machines are powered on and have VMware Tools version 8.3.8.9 (ESX 5.0 Update 1) or later installed, you can configure network settings for the replica virtual machines. This option is primarily used for WAN support.

- **Change**—If you have selected to protect a single virtual machine, click this button and specify credentials for the virtual machine.
- **Provide Credentials**—If you have selected to protect multiple virtual machines, you can select one or more virtual machines, click this button and specify credentials for the virtual machines. If necessary, use the credentials button again until all of the virtual machines that



you want to configure network settings for have credentials specified. You can right-click on any virtual machine in the list to access a **Select All** shortcut which will highlight all of the virtual machines in the list.

- **Use advanced settings for replica virtual machine network configuration**—Select this option to enable the replica virtual machine network setting configuration.
- **Advanced Network**—Select the virtual machines that you want to enable the replica virtual machine network setting configuration for.
- **Set Gateway**—If you are protecting multiple virtual machines, click this button to apply the same gateway settings that each source is using to its replica virtual machine. This is like a global update to quickly populate your replica virtual machine network settings. You can make additional modifications to each replica virtual machine's network settings if needed.
- **Set DNS**—If you are protecting multiple virtual machines, click this button to apply the same DNS settings that each source is using to its replica virtual machine. This is like a global update to quickly populate your replica virtual machine network settings. You can make additional modifications to each replica virtual machine's network settings if needed.
- **Network adapters**—Select a network adapter from the source and specify the **Replica IP addresses**, **Replica Default Gateways**, and **Replica DNS Server addresses** to be used after failover. If you add multiple gateways or DNS servers, you can sort them by using the arrow up and arrow down buttons. Repeat this step for each network adapter on the source.




Updates made during failover will be based on the network adapter name when protection is established. If you change that name, you will need to delete the job and re-create it so the new name will be used during failover.

If you update one of the advanced settings (IP address, gateway, or DNS server), then you must update all of them. Otherwise, the remaining items will be left blank. If you do not specify any of the advanced settings, the replica virtual machine will be assigned the same network configuration as the source.

By default, the source IP address will be included in the target IP address list as the default address. If you do not want the source IP address to be the default address on the target after failover, remove that address from the **Replica IP addresses** list.




---

## Virtual Switch Mappings



Virtual Switch Mappings

Map source VSwitches to the target VSwitches:

Source VSwitch ▲	Target VSwitch
 dvPortGroup	dvPortGroup ▼
 dvPortGroup2	dvPortGroup2 ▼
 VM Network	VM Network ▼


**Map source VSwitches to the target VSwitches**—Identify how you want to handle the network mapping after failover. Map each **Source VSwitch** to a **Target VSwitch**. If you reconfigure your virtual switches after you have created your job, you will need to edit the job to update your mappings, if you want to use the new configuration. You can also choose to failover the NIC and IP addresses but leave them in a not connected state.

## Replication Settings

- **Transmit data after this interval**—Specify the interval (in days, hours, or minutes) for transmitting the replication snapshot. For more details on how the replication interval works, see *Replication process* on page 5.
- **Enable VMware Tools quiescing**—Select this option if you want quiescent replication snapshots (snapshots that are guaranteed to provide consistent application data). You must have VMware Tools installed on the source, your source must be powered on, and your source must be Windows 2003 or later. Linux operating systems do not support quiescing.

Quiescing may impact performance on the source because disk operations will be suspended during the snapshot. VMware Tools instructs the applications running on the guest operating system that have registered for quiescing to suspend activity after they reach a good state. Depending on the type of applications you are running, for example a large transaction to a SQL server database, there may be a delay as applications quiesce, then the operating system quiesces, then the snapshot is taken. (Applications that are not registered for quiescing will have their disk write buffers flushed when the snapshot is taken.)


## ***Encryption***



The screenshot shows a software interface for encryption settings. It features a title bar with a small icon and the word "Encryption". Below the title bar, there is a text label "The changed data can be encrypted before sending to the target." and a checkbox labeled "Enable encryption". The checkbox is currently unchecked.

**Enable encryption**—Enable this option if you want to encrypt the mirroring and replication data before it is sent to the target.

## Snapshots



**Snapshots**

☒ Enable scheduled snapshots

Take snapshots on this interval: 1 Hours

Maximum number of snapshots: 29

A snapshot is an image of the source replica data on the target taken at a single point in time. You can failover to a snapshot. However, you cannot access the snapshot to recover specific files or folders.

Turn on **Enable scheduled snapshots** if you want Double-Take to take snapshots automatically at set intervals.


- **Take snapshots on this interval**—Specify the interval (in days, hours, or minutes) for taking snapshots.
- **Maximum number of snapshots**—Because of VMware snapshot limitations and Double-Take replication processing, the maximum number of snapshots that you can retain is 29. At this point, the oldest snapshot will be deleted when a new snapshot needs to be created. If desired, you can decrease the number of snapshots that will be retained.



Snapshots are stored on the target datastore, so be sure that you have selected a datastore that has enough space for the replica virtual machine and the snapshots.

See *Replication process* on page 5 for details on how the snapshot of the source replica on the target works with the replication process.

## Compression



To help reduce the amount of bandwidth needed to transmit Double-Take data, compression allows you to compress data prior to transmitting it across the network. In a WAN environment this provides optimal use of your network resources. If compression is enabled, the data is compressed before it is transmitted from the source. When the target receives the compressed data, it decompresses it and then writes it to disk. You can set the level from **Minimum** to **Maximum** to suit your needs.

Keep in mind that the process of compressing data impacts processor usage on the source. If you notice an impact on performance while compression is enabled in your environment, either adjust to a lower level of compression, or leave compression disabled. Use the following guidelines to determine whether you should enable compression.

- If data is being queued on the source at any time, consider enabling compression.
- If the server CPU utilization is averaging over 85%, be cautious about enabling compression.
- The higher the level of compression, the higher the CPU utilization will be.
- Do not enable compression if most of the data is inherently compressed. Many image (.jpg, .gif) and media (.wmv, .mp3, .mpg) files, for example, are already compressed. Some images files, such as .bmp and .tif, are decompressed, so enabling compression would be beneficial for those types.
- Compression may improve performance even in high-bandwidth environments.
- Do not enable compression in conjunction with a WAN Accelerator. Use one or the other to compress Double-Take data.



All jobs from a single source connected to the same IP address on a target will share the same compression configuration.

12. Click **Next** to continue.
13. Double-Take validates that your source and target are compatible. The **Summary** page displays your options and validation items.

Errors are designated by a white X inside a red circle. Warnings are designated by a black exclamation point (!) inside a yellow triangle. A successful validation is designated by a white checkmark inside a green circle. You can sort the list by the icon to see errors, warnings, or successful validations together. Click on any of the validation items to see details. You must correct any errors before you can enable protection. Depending on the error, you may be able to click **Fix** or **Fix All** and let Double-Take correct the problem for you. For those errors that Double-Take cannot correct automatically, you will need to modify the source or target to correct the error, or you can select a different target. You must revalidate the selected servers, by clicking **Recheck**, until the validation check passes without errors.

After a job is created, the results of the validation checks are logged to the job log.

14. Once your servers have passed validation and you are ready to establish protection, click **Finish**, and you will automatically be taken to the **Manage Jobs** page.

---

## Chapter 4 Managing and controlling agentless vSphere jobs

The **Manage Jobs** page allows you to view status information about your jobs. You can also control your jobs from this page.

The jobs displayed in the right pane depend on the server group folder selected in the left pane. Every job for each server in your console session is displayed when the **Jobs on All Servers** group is selected. If you have created and populated server groups (see *Managing servers* on page 60), then only the jobs associated with the server or target servers in that server group will be displayed in the right pane.

### ***Overview job information displayed in the top pane***

The top pane displays high-level overview information about your jobs.

---

#### **Column 1 (Blank)**

The first blank column indicates the state of the job.



The job is in a healthy state.



The job is in a warning state. This icon is also displayed on any server groups that you have created that contain a job in a warning state.



The job is in an error state. This icon is also displayed on any server groups that you have created that contain a job in an error state.



The job is in an unknown state.

#### **Job**

The name of the job

#### **Source Server**

The name of the source. This could be the name or IP address of your source.

#### **Target Server**

The name of the target. This could be the name or IP address of your target.

#### **Job Type**

Each job type has a unique job type name. This job is an Agentless vSphere job. For a complete list of all job type names, press F1 to view the Double-Take Console online help.



## Activity

There are many different **Activity** messages that keep you informed of the job activity. Most of the activity messages are informational and do not require any administrator interaction. If you see error messages, check the job details. Keep in mind that **Idle** indicates console to server activity is idle, not that your servers are idle.

## Mirror Status

- **In Progress**—Data is currently being mirrored.
- **Idle**—Data is not being mirrored.
- **Unknown**—The console cannot determine the status.

## Replication Status

- **In Progress**—Data is being replicated to the target.
- **Ready**—There is no data to replicate.
- **Unknown**—The console cannot determine the status.

## Transmit Mode

- **Active**—Data is being transmitted to the target.
  - **Unknown**—The console cannot determine the status.
-

## ***Detailed job information displayed in the bottom pane***

The details displayed in the bottom pane of the **Manage Jobs** page provide additional information for the job highlighted in the top pane. If you select multiple jobs, the details for the first selected job will be displayed.

---

### **Name**

The name of the job

### **Target data state**

This field is not applicable to agentless vSphere jobs.

### **Mirror remaining**

The total number of mirror bytes that are remaining to be sent from the source to the target

### **Mirror skipped**

This field is not applicable to agentless vSphere jobs.

### **Replication queue**

This field is not applicable to agentless vSphere jobs.

### **Disk queue**

This field is not applicable to agentless vSphere jobs.

### **Bytes sent**

The total number of mirror and replication bytes that have been transmitted to the target. If you reset the target replication appliance, this value will be reset.

### **Bytes sent (compressed)**

The total number of compressed mirror and replication bytes that have been transmitted to the target. If compression is disabled, this statistic will be the same as **Bytes sent**.

### **Connected since**

This field is not applicable to agentless vSphere jobs.

### **Recent activity**

Displays the most recent activity for the selected job, along with an icon indicating the success or failure of the last initiated activity. Click the link to see a list of recent activities for the selected job. You can highlight an activity in the list to display additional details about the activity.

**Additional information**

Depending on the current state of your job, you may see additional information displayed to keep you informed about the progress and status of your job. If there is no additional information, you will see (None) displayed.

**Controller appliance**

The controller appliance used by the replication appliances for this job

**Source vCenter/ESXi host**

The vCenter or ESXi server that the source is running on

**Source virtual machine**

The source virtual machine that is being protected

**Target vCenter/ESXi host**

The vCenter or ESXi server that the replica virtual machine is running on

**Target datastore**

The datastore on the target where the replica virtual machine is located

---

## Job controls

You can control your job through the toolbar buttons available on the **Manage jobs** page. If you select multiple jobs, some of the controls will apply only to the first selected job, while others will apply to all of the selected jobs. For example, **View Job Details** will only show details for the first selected job, while **Stop** will stop protection for all of the selected jobs.

If you want to control just one job, you can also right click on that job and access the controls from the pop-up menu.

---

### Create a New Job

This button leaves the **Manage Jobs** page and opens the **Get Started** page.

### View Job Details

This button leaves the **Manage Jobs** page and opens the **View Job Details** page.

### Delete

Stops (if running) and deletes the selected jobs.

If you no longer want to protect the source and no longer need the replica of the source on the target, select to delete the associated replica virtual machine. Selecting this option will remove the job and completely delete the replica virtual machine on the target.

If you no longer want to mirror and replicate data from the source to the target but still want to keep the replica of the source on the target, select to keep the associated replica virtual machine.

### Provide Credentials

Changes the login credentials that the job (which is on the target machine) uses to authenticate to the servers in the job. This button opens the Provide Credentials dialog box where you can specify the new account information and which servers you want to update. See *Providing server credentials* on page 66. You will remain on the **Manage Jobs** page after updating the server credentials. If your servers use the same credentials, make sure you also update the credentials on the **Manage Servers** page so that the Double-Take Console can authenticate to the servers in the console session. See *Managing servers* on page 60.

### View Recent Activity

Displays the recent activity list for the selected job. Highlight an activity in the list to display additional details about the activity.

**Start** 

Starts the selected jobs.

**Pause** 

Agentless vSphere jobs cannot be paused.

**Stop** 

Stops the selected jobs. The jobs remain available in the console, but there will be no mirroring or replication data transmitted from the source to the target.

**Take Snapshot** 

Snapshots are not applicable to agentless vSphere jobs.

**Manage Snapshots** 

Snapshots are not applicable to agentless vSphere jobs.

**Failover or Cutover** 

Starts the failover process. See *Failing over agentless vSphere jobs* on page 55 for the process and details of failing over an agentless vSphere job.

**Failback** 

Starts the failback process. Failback does not apply to agentless vSphere jobs.

**Restore** 

Starts the restoration process. Restore does not apply to agentless vSphere jobs.

**Reverse** 

Reverses protection. Reverse protection does not apply to agentless vSphere jobs.

**Undo Failover** 

Cancels failover by undoing it. Undo does not apply to agentless vSphere jobs.

**View Job Log** 

Opens the job log. On the right-click menu, this option is called **View Logs**, and you have the option of opening the job log, source server log (which is the source replication appliance), or target server log (which is the target replication appliance).

If you need to manually collect agentless vSphere job logs, perform the following steps on each controller and replication appliance.

1. Connect to the appliance using an ssh client, like Putty.
2. Change to the doubletake directory using `cd /opt/visionsolutions/doubletake`.
3. Run the following command (exactly as below without substitutions) to create an archive called `server.tgz` in the doubletake directory.

```
tar czvf $(hostname).tgz bin data etc log
```

4. You can then copy (using a tool like WinSCP) or FTP the file to another location, if needed.

### Other Job Actions

Opens a small menu of other job actions. These job actions are not available for agentless vSphere jobs.

### Filter

Select a filter option from the drop-down list to only display certain jobs. You can display **Healthy jobs**, **Jobs with warnings**, or **Jobs with errors**. To clear the filter, select **All jobs**. If you have created and populated server groups, then the filter will only apply to the jobs associated with the server or target servers in that server group. See *Managing servers* on page 60.

### Type a server name

Displays only jobs that contain the text you entered. If you have created and populated server groups, then only jobs that contain the text you entered associated with the server or target servers in that server group will be displayed. See *Managing servers* on page 60.

### Overflow Chevron

Displays any toolbar buttons that are hidden from view when the window size is reduced.

# Viewing agentless vSphere job details

From the **Manage Jobs** page, highlight the job and click **View Job Details** in the toolbar.

Review the following table to understand the detailed information about your job displayed on the **View Job Details** page.

---

## Job name

The name of the job

## Job type

Each job type has a unique job type name. This job is an Agentless vSphere job. For a complete list of all job type names, press F1 to view the Double-Take Console online help.

## Health



The job is in a healthy state.



The job is in a warning state.



The job is in an error state.



The job is in an unknown state.

## Activity

There are many different **Activity** messages that keep you informed of the job activity. Most of the activity messages are informational and do not require any administrator interaction. If you see error messages, check the rest of the job details.

## Connection ID

The incremental counter used to number connections. The number is incremented when a connection is created. It is also incremented by internal actions, such as an auto-disconnect and auto-reconnect. The lowest available number (as connections are created, stopped, deleted, and so on) will always be used. The counter is reset to one each time the Double-Take service is restarted.

## Transmit mode

- **Active**—Data is being transmitted to the target.
- **Unknown**—The console cannot determine the status.

## Target data state

This field is not applicable to agentless vSphere jobs.

## Target route

This field is not applicable to agentless vSphere jobs.

### Compression

- **On / Level**—Data is compressed at the level specified.
- **Off**—Data is not compressed.

### Encryption

- **On**—Data is being encrypted before it is sent from the source to the target.
- **Off**—Data is not being encrypted before it is sent from the source to the target.

### Bandwidth limit

This field is not applicable to agentless vSphere jobs.

### Connected since

This field is not applicable to agentless vSphere jobs.

### Additional information

Depending on the current state of your job, you may see additional information displayed to keep you informed about the progress and status of your job. If there is no additional information, you will see (None) displayed.

### Mirror status

- **In Progress**—Data is currently being mirrored.
- **Idle**—Data is not being mirrored.
- **Unknown**—The console cannot determine the status.

### Mirror percent complete

The percentage of the mirror that has been completed

### Mirror remaining

The total number of mirror bytes that are remaining to be sent from the source to the target

### Mirror skipped

This field is not applicable to agentless vSphere jobs.

### Replication status

- **In Progress**—Data is being replicated to the target.
- **Ready**—There is no data to replicate.
- **Unknown**—The console cannot determine the status.

### Replication queue

This field is not applicable to agentless vSphere jobs.

### Disk queue

This field is not applicable to agentless vSphere jobs.



**Bytes sent**

The total number of mirror and replication bytes that have been transmitted to the target

**Bytes sent compressed**

The total number of compressed mirror and replication bytes that have been transmitted to the target. If compression is disabled, this statistic will be the same as **Bytes sent**.

---

## Validating an agentless vSphere job

Over time, you may want to confirm that any changes in your network or environment have not impacted your Double-Take job. Use these instructions to validate an existing job.

1. From the **Manage Jobs** page, highlight the job and click **View Job Details** in the toolbar.
2. In the **Tasks** area on the right on the **View Job Details** page, click **Validate job properties**.
3. Errors are designated by a white X inside a red circle. Warnings are designated by a black exclamation point (!) inside a yellow triangle. A successful validation is designated by a white checkmark inside a green circle. You can sort the list by the icon to see errors, warnings, or successful validations together. Click on any of the validation items to see details. You must correct any errors before you can enable protection. Depending on the error, you may be able to click **Fix** or **Fix All** and let Double-Take correct the problem for you. For those errors that Double-Take cannot correct automatically, you will need to modify the source or target to correct the error, or you can select a different target. You must revalidate the selected servers, by clicking **Recheck**, until the validation check passes without errors.
4. Once your servers have passed validation, click **Close**.

## Editing an agentless vSphere job

Use these instructions to edit an agentless vSphere job.

1. From the **Manage Jobs** page, highlight the job and click **View Job Details** in the toolbar.
2. In the **Tasks** area on the right on the **View Job Details** page, click **Edit job properties**.
3. You will see the same options for your agentless vSphere job as when you created the job, but you will not be able to edit all of them. If desired, edit those options that are configurable for an existing job. See *Creating an agentless vSphere job* on page 25 for details on each job option.



Changing some options may require Double-Take to automatically disconnect, reconnect, and remirror the job.

---

4. Click **Next** to continue.
5. Double-Take validates that your source and target are compatible. The **Summary** page displays your options and validation items.


Errors are designated by a white X inside a red circle. Warnings are designated by a black exclamation point (!) inside a yellow triangle. A successful validation is designated by a white checkmark inside a green circle. You can sort the list by the icon to see errors, warnings, or successful validations together. Click on any of the validation items to see details. You must correct any errors before you can enable protection. Depending on the error, you may be able to click **Fix** or **Fix All** and let Double-Take correct the problem for you. For those errors that Double-Take cannot correct automatically, you will need to modify the source or target to correct the error, or you can select a different target. You must revalidate the selected servers, by clicking **Recheck**, until the validation check passes without errors.

After a job is created, the results of the validation checks are logged to the job log.

6. Once your servers have passed validation and you are ready to update your job, click **Finish**.

# Viewing an agentless vSphere job log

You can view a job log file through the Double-Take Console by selecting **View Job Log** from the toolbar on the **Manage Jobs** page. Separate logging windows allow you to continue working in the Double-Take Console while monitoring log messages. You can open multiple logging windows for multiple jobs. When the Double-Take Console is closed, all logging windows will automatically close.



Time	Description
2/14/2012 6:48:46 AM	Target beta is a NOT a cluster. Setting JobFilePath default
2/14/2012 6:48:47 AM	Entered TopState
2/14/2012 6:48:47 AM	Entered UninitializedState
2/14/2012 6:48:47 AM	Attaching to engine monitor 00000000-0000-0000-0000-000000000000
2/14/2012 6:48:47 AM	Changing to StoppedState from UninitializedState in response to InitializeEvent consumed...
2/14/2012 6:48:47 AM	Exited UninitializedState
2/14/2012 6:48:47 AM	Entered InitializedState
2/14/2012 6:48:47 AM	Entered StoppedState
2/14/2012 6:48:47 AM	Stopping monitor ab2268f7-85c6-4b68-819c-3d2912f5380a: name = FilesAndFolders_a6cb...
2/14/2012 6:48:47 AM	Successfully created monitor 618b51de-70f0-418b-9869-169f6f7d7049
2/14/2012 6:48:47 AM	Changing to StartingState from StoppedState in response to StartEvent consumed by Stop...
2/14/2012 6:48:47 AM	Exited StoppedState
2/14/2012 6:48:47 AM	Entered StartingState
2/14/2012 6:48:48 AM	Event log entry written: '6008'.
2/14/2012 6:48:48 AM	Target beta is not clustered
2/14/2012 6:48:48 AM	Changing to RunningState from StoppedState in response to StartEvent consumed by Stop...
2/14/2012 6:48:48 AM	Exited StoppedState
2/14/2012 6:48:48 AM	Entered RunningState
2/14/2012 6:48:48 AM	Starting monitor ab2268f7-85c6-4b68-819c-3d2912f5380a: name = FilesAndFolders_a6cbf...
2/14/2012 6:48:48 AM	Entered SucceededState
2/14/2012 6:48:48 AM	Successfully created connection 985ae0ce-bbba-47a2-84ec-5fa79da80174 connecting Files...
2/14/2012 6:48:48 AM	Waiting for source endpoint of " to be established (00:10:00)
2/14/2012 6:48:50 AM	Established source endpoint of '112.42.74.29:6320' for engine connection with replication s...
2/14/2012 6:48:50 AM	Changing to ProtectingState from StartingState in response to StartSucceededEvent consu...
2/14/2012 6:48:50 AM	Exited StartingState
2/14/2012 6:48:50 AM	Entered ProtectingState
2/14/2012 6:48:50 AM	Event log entry written: '6004'.
2/14/2012 6:48:52 AM	Changing to MirroringState from ProtectingState in response to MirroringEvent consumed b...
2/14/2012 6:48:52 AM	Entered MirroringState
2/14/2012 6:48:52 AM	Changing to SynchronizedState from MirroringState in response to MirrorCompletedEvent c...
2/14/2012 6:48:52 AM	Exited MirroringState
2/14/2012 6:48:52 AM	Entered SynchronizedState
2/14/2012 7:05:45 AM	Event log entry written: '6008'.
2/14/2012 7:05:48 AM	Changing to MirroringState from SynchronizedState in response to MirroringEvent consume...
2/14/2012 7:05:48 AM	Exited SynchronizedState
2/14/2012 7:05:48 AM	Entered MirroringState
2/14/2012 7:05:51 AM	Changing to SynchronizedState from MirroringState in response to MirrorIdleEvent consum...
2/14/2012 7:05:51 AM	Exited MirroringState
2/14/2012 7:05:51 AM	Entered SynchronizedState

The following table identifies the controls and the table columns in the **Job logs** window.

**Start** 

This button starts the addition and scrolling of new messages in the window.

**Pause** 

This button pauses the addition and scrolling of new messages in the window. This is only for the **Job logs** window. The messages are still logged to their respective files on the server.

**Copy** 

This button copies the messages selected in the **Job logs** window to the Windows clipboard.

### Clear

This button clears the **Job logs** window. The messages are not cleared from the respective files on the server. If you want to view all of the messages again, close and reopen the **Job logs** window.

### Time

This column in the table indicates the date and time when the message was logged.

### Description

This column in the table displays the actual message that was logged.

---

## Updating to a new controller appliance

Use the following process to update an existing job to a new controller appliance.

1. Deploy a new controller appliance using a new name and IP address. See *Installing the Double-Take replication or controller appliance* on page 11.
2. Make sure your old controller appliance is powered off.
3. Remove the old controller appliance from the Double-Take Console using the **Remove Server** button on the **Manage Servers** page.
4. Add the new controller appliance to the Double-Take Console. See *Adding controller appliances* on page 21.
5. Complete a host transfer of the license from the old controller appliance, adding that transferred license to the new controller appliance. See *Server licensing* on page 71.
6. Associate your replication appliances with the new controller appliance. See *Adding replication appliances* on page 24.

After you have associated your replication appliances with your new controller appliance, your existing job will appear in the console.

# Failing over agentless vSphere jobs

When you are ready to failover, you can start it manually from the console.

1. On the **Manage Jobs** page, highlight the job that you want to failover and click **Failover or Cutover** in the toolbar.
2. Select the type of failover to perform.
  - **Failover to live data**—Select this option to initiate a full, live failover using the last complete replication cycle. This option will shutdown the source machine (if it is online), stop the protection job, and start the replica virtual machine on the target with full network connectivity.
  - **Perform test failover**—This option is not available for agentless vSphere jobs.
  - **Failover to a snapshot**—Select this option to initiate a full, live failover without using the last replication cycle. Instead, select a snapshot and the data on the target will be reverted to that snapshot. This option will not be available if there are no snapshots on the target.
3. Normally, you would select how you want to handle the data in the target queue. However, these options are not currently available.
4. When you are ready to begin failover, click **Failover**.

---

## Chapter 5 Double-Take Console

Each time you open the Double-Take Console, you start at the **Home** page. This page provides a high-level overview of the status of your jobs.

The appearance of the **Home** page is the same for all users. However, other console pages may have variances in the appearance depending on the Double-Take products that you have installed, the Double-Take activation codes on your servers, and the type of job you are working with.

- **Headlines**—The top section gives a quick overview of any jobs that require attention as well as providing quick access buttons.
  - **These jobs require attention**—Any jobs that require attention (those in an error state) are listed. You will see the source and target server names listed, as well as a short description of the issue that requires your attention. If the list is blank, there are no jobs that require immediate attention.
  - **View**—If you highlight a job in the list and click **View**, you will go to the **View Job Details** page where you can see more detailed information about the job.
  - **Tools**—Select this drop-down list to launch other Vision Solutions consoles.
- **Servers Summary**—The middle section summarizes the servers in your console.
  - **Total number of servers**—This field displays the number of servers that you have been added to the console.
  - **View all servers**—Select this link to go to the **Manage Servers** page where you can view, edit, add, remove, or manage the servers in your console.
- **Jobs Summary**—The bottom section summarizes the jobs in your console.
  - **Total number of jobs**—This field displays the number of jobs running on the servers in your console.
  - **View jobs with errors**—Select this link to go to the **Manage Jobs** page, where the **Filter: Jobs with errors** will automatically be applied.
  - **View jobs with warnings**—Select this link to go to the **Manage Jobs** page, where the **Filter: Jobs with warnings** will automatically be applied.
  - **View all jobs**—Select this link to go to the **Manage Jobs** page and view all jobs.

At the bottom of the Double-Take Console, you will see a status bar. At the right side, you will find links for **Jobs with warnings** and **Jobs with errors**. This lets you see quickly, no matter which page of the console you are on, if you have any jobs that need your attention. Select this link to go to the **Manage Jobs** page, where the appropriate **Filter: Jobs with warnings** or **Filter: Jobs with errors** will automatically be applied.



## Double-Take Console requirements

You must meet the following requirements for the Double-Take Console.

- **Operating system**—The Double-Take Console can be run from a Windows source or target. It can also be run from a 32-bit or 64-bit physical or virtual machine running Windows 8, Windows 7, Windows Vista, or Windows XP Service Pack 2 or later.
- **Microsoft .NET Framework**—Microsoft .NET Framework version 3.5 Service Pack 1 is required. This version is not included in the .NET version 4.0 release. Therefore, even if you have .NET version 4.0 installed, you will also need version 3.5.1. For Windows 2008 and earlier, you can install this version from the Double-Take DVD, via a web connection during the Double-Take installation, or from a copy you have obtained manually from the [Microsoft web site](#). For Windows 2008 R2 and later, you need to enable it through Windows features.
- **Screen resolution**—For best results, use a 1024x768 or higher screen resolution.



The Double-Take installation prohibits the console from being installed on Server Core. Because Windows 2012 allows you to switch back and forth between Server Core and a full installation, you may have the console files available on Server Core, if you installed Double-Take while running in full operating system mode. In any case, you cannot run the Double-Take Console on Server Core.

---

# Console options

There are several options that you can set that are specific to the Double-Take Console.

- **Monitoring interval**—Specifies how often, in seconds, the console refreshes the monitoring data. The servers will be polled at the specified interval for information to refresh the console.
- **Automatic retry**—This option will have the console automatically retry server login credentials, after the specified retry interval, if the server login credentials are not accepted. Keep in mind the following caveats when using this option.
  - This is only for server credentials, not job credentials.
  - A set of credentials provided for or used by multiple servers will not be retried for the specified retry interval on any server if it fails on any of the servers using it.
  - Verify your environment's security policy when using this option. Check your policies for failed login lock outs and resets. For example, if your policy is to reset the failed login attempt count after 30 minutes, set this auto-retry option to the same or a slightly larger value as the 30 minute security policy to decrease the chance of a lockout.
  - Restarting the Double-Take Console will automatically initiate an immediate login.
  - Entering new credentials will initiate an immediate login using the new credentials.
- **Retry on this interval**—If you have enabled the automatic retry, specify the length of time, in minutes, to retry the login.
- **Default port for XML web services protocol**—Specifies the port that the console will use when sending and receiving data to Double-Take servers. By default, the port is 6325. Changes to the console port will not take effect until the console is restarted.
- **Default port for legacy protocol**—If you are using an older Double-Take version, you will need to use the legacy protocol port. This applies to Double-Take versions 5.1 or earlier.
- **Export Diagnostic Data**—This button creates a raw data file that can be used for debugging errors in the Double-Take Console. Use this button as directed by technical support.
- **View Log File**—This button opens the Double-Take Console log file. Use this button as directed by technical support.
- **View Data File**—This button opens the Double-Take Console data file. Use this button as directed by technical support.
- **Automatically check for updates**—By default, each time the console is started, it will automatically check the Vision Solutions web site to see if there is updated console software available. If there is updated console software available, an **Automatic Updates** section will appear on the **Home** page. Click **Get the latest update** to download and install the updated console software.

If you want to disable the automatic check for updates, click **Change automatic updates** or select **Options** from the toolbar. On the **Options** page, deselect **Automatically check for updates** to disable the automatic check.

You can also manually check for updates by selecting **Help, Check for Updates**.

- **Update available**—If there is an update available, click **Get Update**. The dialog box will close and your web browser will open to the Vision Solutions web site where you can download and install the update.
- **No update available**—If you are using the most recent console software, that will be indicated. Click **Close**.

- **No connection available**—If the console cannot contact the update server or if there is an error, the console will report that information. The console log contains a more detailed explanation of the error. Click **Check using Browser** if you want to open your browser to check for console software updates. You will need to use your browser if your Internet access is through a proxy server.
  - **Enable license inventory**—This option allows you to use this console to manage the Double-Take licenses assigned to your organization. When this option is enabled, the **Manage License Inventory** page is also enabled. See the Double-Take Console for details on managing your license inventory.
- 



The license inventory feature may not appear in your console if your service provider has restricted access to it.

---

- **Default Installation Options**—These fields are not used for agentless vSphere protection.

---

## Chapter 6 Managing servers

The **Manage Servers** page allows you to view, edit, add, remove, or manage the servers in your console.

You can also organize the servers that are in your console into groups, allowing you to filter the servers you are viewing based on your organization. The servers displayed in the right pane depend on the server group folder selected in the left pane. Every server in your console session is displayed when the **All Servers** group is selected. If you have created and populated server groups under **My Servers**, then only the servers in the selected group will displayed in the right pane.



If you have uninstalled and reinstalled Double-Take on a server, you may see the server twice on the **Manage Servers** page because the reinstall assigns a new unique identifier to the server. One of the servers (the original version) will show with the red X icon. You can safely remove that server from the console.

---

### *Right pane display*

The following table identifies the columns displayed in the right pane of the **Manage Servers** page.

---

#### Column 1 (Blank)

The first blank column indicates the machine type.



Double-Take source or target server which could be a physical server, virtual machine, or a cluster node



Double-Take source or target server which is a Windows cluster



VMware server which could be a vCenter server or an ESX or ESXi host.



Double-Take controller appliance



Double-Take replication appliance



Double-Take Reporting Service server



Offline server which means the console cannot communicate with this machine.




Server error which means the console can communicate with the machine, but it cannot communicate with Double-Take on it.


#### Column 2 (Blank)

The second blank column indicates the security level

 Processing—The console is attempting to communicate with machine.

 Administrator access—This level grants full control.

 Monitor only access—This level grants monitoring privileges only.

 No security access—This level does not allow monitoring or control.

## Server

The name or IP address of the server. If you have specified a reserved IP address, it will be displayed in parenthesis.

## Activity

There are many different **Activity** messages that keep you informed of the server activity. Most of the activity messages are informational and do not require any administrator interaction. If you see error messages, check the server details. See *Viewing server details* on page 67.

## Version

The product version information

## Licensing Status

The status of the license on the server. If your license is expired, any jobs using that server will be in an error state.

## Product

The Double-Take products licensed for the server or the Double-Take role for the server.

## Activation Code

The activation codes associated with the products licensed for the server. If your license is not valid for the operating system on your server, the activation code will be identified as Invalid Activation Code. There will be no activation code listed for those servers that are not licensed, like a VMware server.

## Serial Number

The serial number associated with the activation code

---

## Main toolbar and right-click menu

The following options are available on the main toolbar of the **Manage Servers** page and the right-click menu. Some of the options are only available in the right-click menu. Each of the options control the server that is selected in the right pane.

---

### Add Servers

Adds a new server. This button leaves the **Manage Servers** page and opens the **Add Servers** page. See *Adding controller appliances* on page 21.

### Add Replication Appliance

Adds a new replication appliance. You must have a controller appliance already inserted in your console before you can add any replication appliances. This button leaves the **Manage Servers** page and opens the **Add Replication Appliances** page. You can also add replication appliances by editing a controller appliance's server properties. See *Controller appliance associations properties* on page 70.

### View Server Details

Views detailed information about a server. This button leaves the **Manage Servers** page and opens the **View Server Details** page. See *Viewing server details* on page 67.

### Remove Server

Removes the server from the console. For agentless vSphere jobs, you cannot remove replication appliances from the **Manage Servers** page. You must remove the replication appliance from the controller appliance's server properties (see *Controller appliance associations properties* on page 70) or from the Add Replication Appliance page (see *Adding replication appliances* on page 24). Keep in mind, if you remove a controller appliance from the console without removing the replication appliance associations, the replication appliances will still be associated with that controller appliance if you add the controller appliance back into this or into another console.

### Provide Credentials

Changes the login credentials that the Double-Take Console use to authenticate to a server. This button opens the **Provide Credentials** dialog box where you can specify the new account information. See *Providing server credentials* on page 66. You will remain on the **Manage Servers** page after updating the server credentials.

## Manage Group Assignments

Allows you to assign, move, and remove the selected server from specific server groups. This button opens the Manage Group Assignments dialog box where you can assign and unassign the server to specific server groups. The server will appear in server groups marked with a checkmark, and will not appear in groups without a checkmark. Servers assigned to a server group will automatically appear in parent server groups.

## Install

Installs or upgrades Double-Take on the selected server. This option is not applicable to agentless vSphere protection.

## Uninstall

Uninstalls Double-Take on the selected server. This option is not applicable to agentless vSphere protection.

## View Server Events

Views event messages for a server. The option is not applicable to agentless vSphere protection.

## View Server Logs

Views the Double-Take logs messages for a server. This button opens the **Logs** window. This separate window allows you to continue working in the Double-Take Console while monitoring log messages. You can open multiple logging windows for multiple servers. When the Double-Take Console is closed, all logging windows will automatically close.

## Refresh

Refreshes the status of the selected servers.

## Gather Support Diagnostics

Executes the diagnostic DTInfo utility which collects configuration data for use when reporting problems to technical support. It gathers Double-Take log files; Double-Take and system settings; network configuration information such as IP, WINS, and DNS addresses; and other data which may be necessary for technical support to troubleshoot issues. You will be prompted for a location to save the resulting file which is created with the information gathered. Because this utility is gathering several pieces of information, across the network to your console machine, it may take several minutes to complete the information gathering and sending the resulting file to the console machine.

This option is disabled for replication appliances. That data will be collected when data is collected for a controller appliance.

### **View Replication Service Details**

Views the replication service details for a server. This option is not applicable to agentless vSphere servers.

### **Overflow Chevron**



Displays any toolbar buttons that are hidden from view when the window size is reduced.

---



## ***Left pane toolbar***

Between the main toolbar and the left pane is a smaller toolbar. These toolbar options control the server groups in the left pane.

---

### **Create New Server Group**

Creates a new server group below the selected group

### **Rename Server Group**

Allows you to rename the selected server group

### **Delete Server Group**

Deletes the selected server group. This will not delete the servers in the group, only the group itself.

### **Overflow Chevron**

Displays any toolbar buttons that are hidden from view when the window size is reduced.

---

## Providing server credentials

To update the security credentials used for a specific server, select **Provide Credentials** from the toolbar on the **Manage Servers** page. When prompted, specify the **User name**, **Password**, and **Domain** of the account you want to use for this server. Click **OK** to save the changes.



This process is not applicable to Double-Take replication appliances. To update the credentials for replication appliances, use the controller appliance's server properties. See *Controller appliance associations properties* on page 70.

---

# Viewing server details

The **View Server Details** page allows you to view details about that particular server. The server details vary depending on the type of server or appliance you are viewing.

---

## Server name

The name or IP address of the server. If you have specified a reserved IP address, it will be displayed in parenthesis.

## Operating system

The server's operating system version

## Roles

The role of this server in your Double-Take environment. In some cases, a server can have more than one role.

- **EngineRole**—Source or target server
- **ProxyRole**—A Linux appliance for a full server to ESX appliance job
- **ProxiedRole**—A Linux source server for a full server to ESX appliance job
- **ControllerRole**—Controller appliance for an agentless vSphere job
- **ReplicationApplianceRole**—Replication appliance for an agentless vSphere job
- **Reporting Service**—Double-Take Reporting Service server

## Status

There are many different **Status** messages that keep you informed of the server activity. Most of the status messages are informational and do not require any administrator interaction. If you see error messages, check the rest of the server details.

## Activity

There are many different **Activity** messages that keep you informed of the server activity. Most of the activity messages are informational and do not require any administrator interaction. If you see error messages, check the rest of the server details.

## Connected via

The IP address and port the server is using for communications. You will also see the Double-Take protocol being used to communicate with server. The protocol will be XML web services protocol (for servers running Double-Take version 5.2 or later) or Legacy protocol (for servers running version 5.1 or earlier).

## Version

The product version information

## Access

The security level granted to the specified user

## User name

The user account used to access the server

## Licensing quantity

The available and total license count for a Double-Take controller appliance

## Licensing

Licensing information for the server

- **Warning or error icon**—Warnings indicate the license is temporary and will expire. Errors indicate the license has expired or it is invalid for the operating system on the server.
- **Product**—The product associated with the license
- **Serial Number**—The serial number associated with the license
- **Expiration Date**—The date the license expires, if there is one
- **Activation Code**—The activation code
- **Licensing Status**—The status of the license on the server. If your license is expired, any jobs using that server will be in an error state.
- **License Type**—The type of Double-Take license

## Source jobs

If you are viewing a replication appliance, you will see a list of any jobs from this server. Double-clicking on a job in this list will automatically open the **View Job Details** page.

## Target jobs

If you are viewing a replication appliance you will see a list of any jobs to this server. Double-clicking on a job in this list will automatically open the **View Job Details** page.

## Associated vCenter/ESXi servers and replication appliances

The vCenter or ESXi servers and the replication appliances that are associated with the controller appliance. To modify the associated appliances, click on the **Edit server properties** link. See *Controller appliance associations properties* on page 70.

---

## Editing server properties

Highlight a server on the **Manage Servers** page and click **View Server Details** from the toolbar. Under **Tasks**, select **Edit server properties**. The **Edit Server Properties** page allows you to view and edit properties for that server. Click on a heading on the **Edit Server Properties** page to expand or collapse a section of properties.

- *Controller appliance associations properties* on page 70—Establishes associations between controller appliances, replication appliances, and vCenter/ESXi servers
- *Server licensing* on page 71—Views, adds, and removes activation codes
- *E-mail notification configuration* on page 73—Configures e-mail notification

## Controller appliance associations properties

The Controller Appliance Associations properties allow you to manage the replication appliances associated with your controller appliance.

- **Provide credentials**—Select this button to update the credentials for the selected vCenter/ESXi server or the replication appliance. When prompted, specify the **User name**, **Password**, and if necessary the **Domain**.
- **Remove**—Select this button to remove the selected machine. If you remove the vCenter/ESXi server, any associated replication appliances will also be removed. If you remove a replication appliance, just that one appliance will be removed. Keep in mind that you cannot remove appliance associations if a job is using the appliance.

# Server licensing

Licensing identifies your Double-Take activation codes.



The fields and buttons in the **Licensing** section will vary depending on your Double-Take Console configuration and the type of activation codes you are using.

---

- **Add activation codes and activation keys**—The activation code and activation key are the Double-Take license which is required on every Double-Take server. They are a 24 character, alpha-numeric code. You can change your activation code without reinstalling, if your license changes.

There are different licenses available depending on the Double-Take product you are using. Agentless vSphere jobs use a quantity license to license a specific number of jobs. See **Total licenses quantity** below for details on how the license quantity (used by the controller appliance) is allocated for agentless vSphere jobs.

To add an activation code and activation key, type in the code and click **Add**. If your console has been enabled to manage your license inventory, click **Choose from inventory** to open the Activation Codes dialog box where you can select the activation codes you want to apply. See *Console options* on page 58 for details on enabling the license inventory.



The license inventory feature cannot be enabled if your service provider has restricted access to it.

---

- **Current activation codes**—The server's current activation codes are displayed.
  - **Warning or error icon**—Warnings indicate the license is temporary and will expire. Errors indicate the license has expired.
  - **Product**—The product associated with the license
  - **Serial Number**—The serial number associated with the license
  - **Expiration Date**—The date the license expires, if there is one
  - **Activation Code**—The activation code

To remove a code, highlight it and click **Remove**. To copy a code, highlight it and click **Copy**.

- **Activation**—If your activation code needs to be activated, you will see an additional **Activation** section at the bottom of the **Licensing** section. To activate your code, use one of the following procedures.
  - **Activate online**—If you have Internet access, you can activate your license and apply the activated license to the server in one step. Select **Activate Online**. You will not be able to activate a license that has already been activated but has not been deactivated. In that case, you will be prompted to complete a host transfer. Ideally, you should deactivate the license instead of doing a host transfer. See the Double-Take Console online help for details on deactivating licenses and host transfers.

- **Obtain activation key online, then activate**—If you have Internet access, click the hyperlink in the **Activation** section to take you to the web so that you can submit your activation information. Complete and submit the activation form, and you will receive an e-mail with the activation key. Activate your server by entering the activation key in the **Add activation codes and activations keys** field and clicking **Add**.
- **Obtain activation key offline, then activate**—If you do not have Internet access, go to <https://activate.doubletake.com> from another machine that has Internet access. Complete and submit the activation form, and you will receive an e-mail with the activation key. Activate your server by entering the activation key in the **Add activation codes and activations keys** field and clicking **Add**.

The permanent code is specific to this server. It cannot be used on any other server. If the activation code and server do not match, Double-Take will not run.

---



If your activation codes needs to be activated, you will have 14 days to do so.

If you rename a server that has already has a Double-Take license applied to it, for example if you rebuild a server, you will have to perform a host-transfer to continue using that license. This includes changing the case (capitalization) of the server name (upper or lower case or any combination of case).

---



## E-mail notification configuration

You can email Double-Take event messages to specific addresses, using an SMTP mail server. The subject of the email will contain an optional prefix, the event type (information, warning or error), the job name, and the controller appliance name. The body of the message will contain configuration info (date, time, virtual machine names, and so on) and the text of the event messages.

The screenshot shows the 'E-mail Notification' configuration window. It has a title bar with a minimize button and the text 'E-mail Notification'. Inside the window, there is a checkbox labeled 'Enable e-mail notifications' which is checked. To the right of this checkbox is a 'Test' button. Below the checkbox is a text field for 'E-mail server (SMTP):' containing the text 'MailServer'. Underneath is a section for 'Connection Security' with three radio buttons: 'Plain' (selected), 'SSL', and 'SSL/TLS'. Below that is another checked checkbox 'Log on to e-mail server'. This is followed by a 'User name:' field containing 'administrator' and a 'Password:' field filled with dots. Then is a 'From address:' field containing 'admin@domain.com'. Below that is a 'Send to:' field containing 'admin@domain.com; ITSupport@domain.com'. Next is a 'Subject prefix:' field containing 'Double-Take Notification'. Finally, there is a section 'Notify when these events occur:' with a tree view. The tree has three main categories: 'Information' (unchecked), 'Warning' (checked), and 'Error' (checked). Under 'Information' are 'Create job', 'Start job', and 'Stop job' (all unchecked). Under 'Warning' are 'Delete job', 'Failover job', and 'Reverse job' (all checked). Under 'Error' are 'License issue', 'Connection lost', and 'Other error' (all checked).

- **Enable e-mail notification**—This option enables the e-mail notification feature. Any specified notification settings will be retained if this option is disabled.
- **E-mail server**—Specify the name of your SMTP mail server. If necessary, after the e-mail server name, you can include a colon followed by the outgoing e-mail requests port number. For example, you might use gmail.com:465.
- **Connection Security**—Select the type of security for your email server. Check with your e-mail service provider if you do not know your security type.
- **Log on to e-mail server**—If your SMTP server requires authentication, enable this option and specify the **User name** and **Password** to be used for authentication.

- **From address**—Specify the e-mail address that you want to appear in the From field of each Double-Take e-mail message. The address is limited to 256 characters.
- **Send to**—Specify the e-mail addresses that each Double-Take e-mail message should be sent to. Enter the addresses as a comma or semicolon separated list. Each address is limited to 256 characters. You can add up to 256 e-mail addresses.
- **Subject prefix**—The subject of each e-mail notification will be in the format Subject Prefix - Event Type, Job=Job\_Name, Controller=Controller\_Appliance\_Name. The subject prefix is optional. The subject line is limited to 255 characters.

If desired, enter unique text for the **Subject prefix** which will be inserted at the front of the subject line for each Double-Take e-mail message. This will help distinguish Double-Take messages from other messages. This field is optional.


- **Notify when these event occur**—Select each of the events that you want to receive an e-mail notification for. Selecting or deselecting a top level check box (Information, Warning, or Error) will select or deselect all of the items in that category. If desired, you can also select or deselect events individually.

# Viewing server logs

You can view the controller appliance log through the Double-Take Console using either of these two methods.

- On the **Manage Servers** page, highlight a server in the list and click **View Server Logs** from the toolbar.
- On the **Manage Jobs** page, right-click a job and select **View Logs**. Select either the source server log or the target server log.

Separate logging windows allow you to continue working in the Double-Take Console while monitoring log messages. You can open multiple logging windows for multiple servers. When the Double-Take Console is closed, all logging windows will automatically close.



Time	Description	Service
7/30/2013 2:03:51 PM	DTAV Controller Service initializing, build number: 7.0.0.1874.0 on 2013-07-29 22:11:19	controller
7/30/2013 2:03:51 PM		controller
7/30/2013 2:03:51 PM		controller
7/30/2013 2:03:51 PM	save pid to: /var/run/dtav.pid	controller
7/30/2013 2:03:52 PM	Starting scheduler: Unconnected RA Monitor Scheduler, iteration interval, sec: 5	controller
7/30/2013 2:03:53 PM	Starting scheduler: JobCache, iteration interval, sec: 5	controller
7/30/2013 2:03:53 PM	Starting scheduler: ControllerLicenseEnforcement, iteration interval, sec: 36	controller
7/30/2013 2:03:53 PM	https, port 6326: registering SOAP handler for context: /Interop/Virtualization/DTAVReplic...	controller
7/30/2013 2:04:00 PM	https, port 6326: endpoint registered: /Interop/Virtualization/DTAVReplicationApplianceMa...	controller
7/30/2013 2:04:00 PM	https, port 6326: registering SOAP handler for context: /Interop/DoubleTake/Jobs/JobMan...	controller
7/30/2013 2:04:03 PM	https, port 6326: endpoint registered: /Interop/DoubleTake/Jobs/JobManager	controller
7/30/2013 2:04:03 PM	https, port 6326: registering SOAP handler for context: /Interop/DoubleTake/Common/Co...	controller
7/30/2013 2:04:07 PM	https, port 6326: endpoint registered: /Interop/DoubleTake/Common/Contract/Manageme...	controller
7/30/2013 2:04:07 PM	https, port 6326: registering SOAP handler for context: /Interop/Virtualization/DTAVWorkfl...	controller
7/30/2013 2:04:10 PM	https, port 6326: endpoint registered: /Interop/Virtualization/DTAVWorkflowManager	controller
7/30/2013 2:04:10 PM	Starting scheduler: RaServerInfoCache, iteration interval, sec: 5	controller
7/30/2013 2:04:10 PM	https, port 6326: registering SOAP handler for context: /Interop/Virtualization/DTAVServer...	controller
7/30/2013 2:04:13 PM	https, port 6326: endpoint registered: /Interop/Virtualization/DTAVServerManager	controller
7/30/2013 2:04:13 PM	http, port 6325: registering SOAP handler for context: /Interop/Metaservice	controller
7/30/2013 2:04:15 PM	http, port 6325: endpoint registered: /Interop/Metaservice	controller
7/30/2013 2:04:15 PM	DTAV Controller Service started	controller
7/30/2013 2:23:55 PM	adding RA: 172.31.139.146 to Vim: 172.31.0.162	controller
7/30/2013 2:24:05 PM	Adding RA to the connected list: 172.31.139.146	controller
7/30/2013 2:24:06 PM	Add RA: This ESX host cannot be selected since it is managed by VC	controller
7/30/2013 2:24:26 PM	adding RA: 172.31.139.146 to Vim: 172.31.0.172	controller
7/30/2013 2:24:33 PM	Adding RA to the connected list: 172.31.139.146	controller
7/30/2013 2:24:37 PM	RA validated and added. Host ID: 44454c4c-4a00-1054-8036-b9c04f504431	controller
7/30/2013 2:24:51 PM	adding RA: 172.31.139.148 to Vim: 172.31.0.172	controller
7/30/2013 2:24:59 PM	Adding RA to the connected list: 172.31.139.148	controller
7/30/2013 2:25:03 PM	RA validated and added. Host ID: 44454c4c-4a00-1054-8036-b9c04f504431	controller

The following table identifies the controls and the table columns in the **Server logs** window.

## Start

This button starts the addition and scrolling of new messages in the window.

## Pause

This button pauses the addition and scrolling of new messages in the window. This is only for the **Server logs** window. The messages are still logged to their respective files on the server.

### Copy

This button copies the messages selected in the **Server logs** window to the Windows clipboard.

### Clear

This button clears the **Server logs** window. The messages are not cleared from the respective files on the server. If you want to view all of the messages again, close and reopen the **Server logs** window.

### Filter

For controller appliances, there is only one log to view so filtering is not applicable.

### Time

This column in the table indicates the date and time when the message was logged.

### Description

This column in the table displays the actual message that was logged.

### Service

This column in the table indicates the message is from the controller log file.

---

# ***Index***

## **A**

- activation 22
- activation codes 22, 71
- adding controller appliance 21
- agentless vSphere
  - controller appliance 54
  - create job 25
  - edit job 51
  - failover 55
  - job details 47
  - job log 52
  - job validation 50
  - requirements 7
  - source 25
  - target 26
- appliance
  - controller 54

## **C**

- console 56-57
  - controller appliance 21
  - credentials 66
  - options 58
  - replication appliances 24
  - servers 60, 67, 69
- controller appliance
  - updating 54
- create job
  - agentless vSphere 25
- credentials 66
- CustomerCare 2

## **E**

- e-mail 73

## **F**

- failover
  - agentless vSphere 55

## **G**

- getting started 10

## **I**

- installation
  - console 19
  - controller appliance 11
  - replication appliance 11
  - Windows client 19

## **J**

- job 40
  - agentless vSphere 25, 47, 50-51, 55
- job log 52

## **L**

- legal 2
- license 22, 71
- logging 75

## **M**

- managing job 40
- managing servers 60

## **O**

- overview 4, 10, 56

## **P**

- protection
  - agentless vSphere 25

## **R**

- replication appliances 24
- replication process 5
- requirements
  - agentless vSphere 7
  - console 57

resources 2

## **S**

server details 67

server properties 69-71, 73

source

    agentless vSphere 25

## **T**

target

    agentless vSphere 26

technical support 2

## **V**

vSphere

    controller appliance 54

    create job 25

    edit job 51

    failover 55

    job details 47

    job log 52

    job validation 50

    requirements 7

    source 25

    target 26